

Introduction

[Top](#) [Next](#)

Elcomsoft System Recovery helps system administrators reset or recover passwords to local Windows accounts and Microsoft Account in all versions of Windows, assign administrative privileges to any user account, reset expired passwords or export password hashes for offline recovery. The tool can detect encryption and create forensic disk images. Elcomsoft System Recovery is supplied with a bootable Windows PE environment.

Features and Benefits

- Ready to boot with Windows PE (Preinstallation Environment) licensed from Microsoft
- Recovers or resets user and administrative passwords
- Original password recovery may be possible to provide automatic access to EFS-encrypted files
- Unlocks and enables user and administrative accounts
- Assigns administrative privileges to any user account
- Resets or disables password expiry options
- Broad hardware compatibility and genuinely native FAT and NTFS support
- Genuine Windows GUI for convenient operation
- Supports Windows NT 4, Windows 2000, Windows XP, Windows Vista, Windows 7, Windows 8/8.1, Windows 10
- Supports Windows Windows Server 2000/2003/2008/2012/2016/2019 (including Domain Administrator password and all users' passwords)
- Supports US and localized versions of Windows and multilingual user names and passwords
- Detects all Windows installations automatically
- An option to dump hashed passwords from SAM/SYSTEM files or Active Directory database for further analysis and off-line password recovery
- An option to dump Domain Cached Credentials
- Dumps encryption keys for protected drives
- Supports Microsoft Live! accounts
- Resets or searches for SYSKEY startup password
- Password reset for Domain Cached accounts
- Dumps disk encryption keys
- Unlocks BitLocker-encrypted drives
- Locates encrypted virtual machines and extract encryption metadata for subsequent password recovery
- Creates forensic disk or partition images

Ready to Boot, Instant Unlock

Elcomsoft System Recovery makes it easy to create a bootable CD image (ISO) or USB flash drive. No need to create a reach for a Windows setup disks to make one! ElcomSoft has licensed the Windows Preinstallation Environment (Windows PE) directly from Microsoft, allowing the company to distribute the completely working bootable Windows environment based on Windows 10.

If there are no EFS-encrypted files on your Windows account, an instant unlock option is the quickest and easiest way to gain access to user and administrative accounts. Elcomsoft System Recovery resets forgotten passwords with a new password supplied by you, allowing for immediate login without the time-consuming password recovery operations.

Broad Compatibility

Elcomsoft System Recovery bootable environment supports a variety of hardware components including the most popular hard disk controllers thanks to the native Windows drivers. Unlike the various emulation environments, Elcomsoft System Recovery is genuinely compatible with the latest revisions of Microsoft file systems, including the latest versions of the FAT (FAT32, exFAT) and NTFS.

Recovers Original Passwords

Elcomsoft System Recovery can attempt to attack and recover the original password with common passwords and dictionary attacks. Elcomsoft System Recovery checks the locations where system passwords are cached, often allowing for instant password recovery.

Offline password recovery is made possible by dumping hashed passwords from SAM/SYSTEM files or Active Directory database for further analysis off-line analysis. We recommend [Elcomsoft Distributed Password Recovery](#) for highly scalable, GPU-accelerated recovery of system passwords.

This software contains Far Manager
Copyright (c) 1996 Eugene Roshal
Copyright (c) 2000 Far Group
All rights reserved.

End-user license agreement

[Top](#) [Previous](#) [Next](#)

NOTICE TO USER:

THIS IS AN AGREEMENT GOVERNING YOUR USE OF ELCOMSOFT SOFTWARE, FURTHER DEFINED HEREIN AS "PRODUCT," AND THE LICENSOR OF THE PRODUCT IS WILLING TO PROVIDE YOU WITH ACCESS TO THE PRODUCT ONLY ON THE CONDITION THAT YOU ACCEPT ALL OF THE TERMS AND CONDITIONS CONTAINED IN THIS AGREEMENT. BELOW, YOU ARE ASKED TO ACCEPT THIS AGREEMENT AND CONTINUE TO INSTALL OR, IF YOU DO NOT WISH TO ACCEPT THIS AGREEMENT, TO DECLINE THIS AGREEMENT, IN WHICH CASE YOU WILL NOT BE ABLE TO INSTALL OR OPERATE THE PRODUCT. BY INSTALLING THIS PRODUCT YOU ACCEPT ALL THE TERMS AND CONDITIONS OF THIS AGREEMENT. PURCHASE ORDER, SECTIONS OF THE LICENSOR'S WEBSITE AND PRODUCT'S DOCUMENTATION THAT CONTAIN SPECIFIC PROVISIONS AND LIMITATIONS GOVERNING USE OF CERTAIN PRODUCTS ARE INCORPORATED IN THIS AGREEMENT BY REFERENCE AND CONSTITUTE PARTS OF THIS END USER LICENSE AGREEMENT. PLEASE REFER TO SOME IN SPECIFIC CASES.

This Electronic End User License Agreement (the "Agreement") is a legal agreement between you (either an individual or an entity), the licensee, and ElcomSoft Co. Ltd. and its affiliates (collectively, the "Licensor"), regarding the Licensor's software, as applicable pursuant to a valid license, you are about to download and/or other related services, including without limitation a) all of the contents of the files, disk(s), CD-ROM(s) or other media with which this Agreement is provided and including all forms of code, such as source code and object code, (the "Software"), b) all successor upgrades, modified versions, modified modules, revisions, patches, enhancements, fixes, modifications, copies, additions or maintenance releases of the Software, if any, licensed to you by the Licensor (collectively, the "Updates"), and c) related user documentation and explanatory materials or files provided in written, "online" or electronic form (the "Documentation" and together with the Software and Updates, the "Product"). You are subject to the terms and conditions of this End User License Agreement whether you access or obtain the Product directly from the Licensor, or through any other source. For purposes hereof, "you" means the individual person installing or using the Product on his or her own behalf; or, if the Product is being downloaded or installed on behalf of an organization, such as an employer, "you" means the organization for which the Product is downloaded or installed, then the person accepting this agreement represents hereby that such organization has authorized such person to accept this agreement on the organization's behalf. For purposes hereof the term "organization," without limitation, includes any partnership, limited liability company, corporation, association, joint stock company, trust, joint venture, labor organization, unincorporated organization, or governmental authority.

By accessing, storing, loading, installing, executing, displaying, copying the Product into the memory of a Client Device, as defined below, or otherwise benefiting from using the functionality of the Product ("Operating"), you agree to be bound by the terms and conditions of this Agreement. If you do not agree to the terms and conditions of this Agreement, the Licensor is unwilling to license the Product to you. In such event, you may not Operate or use the Product in any way.

BEFORE YOU PUT A CHECKMARK AT THE "I ACCEPT THE AGREEMENT" BUTTON AND PRESS "NEXT," PLEASE CAREFULLY READ THE TERMS AND CONDITIONS OF THIS AGREEMENT, AS SUCH ACTIONS ARE A SYMBOL OF YOUR SIGNATURE AND BY CLICKING ON THE "I ACCEPT THE AGREEMENT" AND "NEXT" BUTTONS, YOU ARE CONSENTING TO BE BOUND BY AND ARE BECOMING A PARTY TO THIS AGREEMENT AND AGREE THAT THIS AGREEMENT IS ENFORCEABLE LIKE ANY WRITTEN NEGOTIATED AGREEMENT SIGNED BY YOU. IF YOU DO NOT AGREE TO ALL OF THE TERMS OF THIS AGREEMENT, CLICK THE "CANCEL" BUTTON AND THE PRODUCT WILL NOT BE INSTALLED ON YOUR CLIENT DEVICE, AS SUCH TERM IS DEFINED BELOW.

For your reference, you may refer to the copy of this Agreement that can be found in the Product Manual for the Software. You may also receive a copy of this Agreement by contacting Licensor at:

<https://www.elcomsoft.com>.

1. Proprietary Rights and Non-Disclosure.

1.1. Ownership Rights. You agree that the Product and the authorship, systems, ideas, methods of operation, documentation and other information contained in the Product, are proprietary intellectual properties and or the valuable trade secrets of the Licensor and are protected by civil and criminal law, and by the law of copyright, trade secret, trademark and patent of the Russian federation, other countries and international treaties. You may use trademarks only insofar as to identify printed output produced by the Product in accordance with accepted trademark practice, including identification of trademark owner's name. Such use of any trademark does not give you any rights of ownership in that trademark. The Licensor and its suppliers own and retain all right, title, and interest in and to the Product, including without limitations any error corrections, enhancements, Updates or other modifications to the Software, whether made by Licensor or any third party, and all copyrights, patents, trade secret rights, trademarks, and other intellectual property rights therein. Your possession, installation or use of the Product does not transfer to you any title to the intellectual property in the Product, and you will not acquire any rights to the Product except as expressly set forth in this Agreement. All copies of the Product made hereunder must contain the same proprietary notices that appear on and in the Product. Except as stated herein, this Agreement does not grant you any intellectual property rights in the Product and you acknowledge that the license granted under this Agreement only provides you with a right of limited use under the terms and conditions of this Agreement.

1.2. Source Code and Modifications. You acknowledge that the source code for the Product is proprietary to the Licensor and constitutes trade secrets of the Licensor. You agree not to modify, or create derivative works based upon the Product in whole or in part nor reverse engineer, decompile, disassemble the source code of the Product in any way.

1.3. Registration Code File and Confidential Information. You agree that, unless otherwise specifically provided herein or agreed by the Licensor in writing, the Product, including the specific design and structure of individual programs and the Product, including without limitation the Registration Code File provided to you by the Licensor and/or its authorized resellers or distributors, constitute confidential proprietary information of the Licensor. For purposes hereof, "Registration Code" shall mean a unique key identification file or a combination of unique electronic characters provided to you by the Licensor confirming the purchase of the license from the Licensor, which may carry the information about the license and the number of permitted users, and enabling the full functionality of the Product in accordance with the license granted under this Agreement. You agree not to transfer, copy, disclose, provide or otherwise make available such confidential information in any form to any third party without the prior written consent of the Licensor. You agree to implement reasonable security measures to protect such confidential information, but without limitation to the foregoing, shall use best efforts to maintain the security of the Registration Code provided to you by the Licensor and/or its authorized resellers or distributors.

2. Grant of License.

2.1. License. The Licensor grants you the following rights ("License") and you hereby agree and accept such License:

a). Trial Version. If you have received, downloaded and/or installed a trial version of the Product and are hereby granted an evaluation license for the Software and you may Operate the Product only for evaluation purposes and only during the single applicable evaluation period of thirty (30) days, unless otherwise indicated, from the date of the initial installation. Trial Version may also have limited functionality of the Product and other limitations that will be communicated to You by the Licensor. Trial Version may have some protection mechanism that prevents its unauthorized use outside of the trial period. Following this test (trial) period of thirty (30) days or any other agreed period, if you wish to continue to use the Product, you must purchase the license. You may not use the Product after expiry of the trial period.

To purchase the license you have to pay for the fully functional version. Upon payment we provide the Registration Code to you. Any use of the Product for other purposes or beyond the applicable evaluation period is strictly prohibited, provided however that, subject to the restrictions contained herein, you may copy and distribute a trial version of the Software without any modifications whatsoever to any third party subject to this Agreement and further provided that you have no technical support rights during the trial period. The unregistered (trial) version may be freely distributed, provided that the distribution package is not modified. No person or company may charge a fee for the distribution of the Product without written permission from the copyright holder.

b). Grant of License. Unless otherwise specifically indicated in your Purchase Order under a valid license (e.g. volume license or any other license) granted by the Licensor, once registered you are granted a non-exclusive and non-transferable license to install one (1) copy of the Product and during the term of your license, subject to the payment of the applicable fees and your compliance with the terms hereof, this Agreement, unless otherwise specifically indicated in your Purchase Order, permits you or any of your employees to Operate one copy of the specified version of the Product, for internal purposes only, on one computer, workstation, or other electronic device of which the software was designed (each a "Client Device"). If you have purchased multiple licenses for the Product, then the number of multiple licenses shall determine the number of copies of the Product you may have and the number of Client Devices on which you may Operate the Product. If the Product is licensed as a suite or bundle with more than one specified software product, this license applies to all such specified software products, subject to any restrictions or usage terms specified on the applicable price list or product packaging that apply to any of such software products individually. Additionally, Licensor reserves the right to provide for specific terms and conditions in the purchased licenses and such terms may be embedded in Registration Code specifying other terms, conditions and restrictions of Operating of the Product. Specific details related to a type of license shall be indicated in your Purchase Order. For specific details relating to some of our Products, their use, operation and possible limitations on use, please refer to the Products section of our website. The Licensor reserves all rights not expressly granted herein.

c). Volume Use. If the Product is licensed with volume license terms specified in the applicable product invoicing, Purchase Order or packaging for the Product, you may make use and install as many additional copies of the Product on the number of Client Devices as the volume license terms specify. You must have a reasonable mechanism in place to ensure that the number of Client Devices on which the Product has been installed does not exceed the number of licenses you have obtained.

d). Multiple Environment Product; Multiple Language Product; Dual Media Product; Multiple Copies; Bundles. If the Product supports multiple platforms or languages, if you receive the Product on multiple media, if you otherwise receive multiple copies of the Product, or if you received the Product bundled with other software, the total number of your Client Devices on which all versions of the Product are installed may not exceed the number of licenses you have obtained from the Licensor. You may not rent, lease, sublicense, lend or transfer any versions or copies of the Product you do not use.

2.2. Back-up Copies. You can make one (1) copy the Product for backup and archival purposes, provided, however, that the original and each copy is kept in your possession or control, and that your installation and use of the Product does not exceed that which is allowed in this Section 2.

2.3. Prohibitions. You may not use, copy, emulate, clone, rent, lease, sell, modify, decompile, disassemble, otherwise reverse engineer, or transfer the licensed program, or any subset of the licensed program, except as provided for in this Agreement including any terms and restrictions provided in your Purchase Order, any respective sections of our website and Product Documentation.

You may not use any of our Products in a way prohibited in the Product Documentation.

You agree not to engage in or to instigate actions that cause harm to ElcomSoft or its other users and customers. Such actions include, but are not limited to, actions resulting in DDOS attacks for any servers,

causing in any way disruption to any services of ElcomSoft or any technology employed by ElcomSoft to provide its Products and respective services, etc.

You agree that we have the sole right to decide what constitutes a violation of the acceptable use described above as well as what is the appropriate severity of any corrective action or remedy to be applied.

Any such unauthorized use shall result in immediate and automatic termination of this license and may result in criminal and/or civil prosecution. Neither ElcomSoft binary code nor source may be used or reverse engineered to re-create the program algorithm, which is proprietary, without written permission of Licensor. All rights not expressly granted here are reserved by ElcomSoft Co. Ltd.

2.4. Registration Code. Registration Code provided by the Licensor constitutes the confidential proprietary information of the Licensor. ElcomSoft Registration Code file may not be distributed, except as stated herein, outside of the area of legal control of the person or persons who purchased the original license, without written permission of the copyright holder. You may not give away, sell or otherwise transfer your Registration Code to a third party. Doing so will result in an infringement of copyright. ElcomSoft Co. Ltd retains the right of claims for compensation in respect of damage which occurred by your giving away the registration code. This claim shall also extend to all costs which ElcomSoft Co. Ltd incurs in defending itself.

2.5. Transfers. Under no circumstances shall Licensee sell, rent, lease, license, sublicense, publish, display, distribute, or otherwise transfer to a third party the Software, any copy thereof, in whole or in part, without Licensor's prior written consent, unless otherwise provided for in this Agreement.

2.6. Acceptance of Licensing Terms. Installing and using the Product signifies acceptance of these terms and conditions of the License. If you do not agree with the terms of the license you must remove all Product files from your storage devices, including any back-up or archival copy, and cease to use the Product.

2.7. Material Terms and Conditions. Licensee specifically agrees that each of the terms and conditions of this Section 2 are material and that failure of Licensee to comply with these terms and conditions shall constitute sufficient cause for Licensor to immediately terminate this Agreement and the License granted under this Agreement. The presence of this Section 2.7 shall not be relevant in determining the materiality of any other provision or breach of this Agreement by either party.

2.8. Term and Termination. The term of this Agreement ("Term") shall begin when you download, access or install the Product or pay the applicable license fees (whichever is earlier) and shall continue for the term specified in your Purchase Order. Without prejudice to any other rights, this Agreement will terminate automatically if you fail to comply with any of the limitations or other requirements described herein. Upon any termination or expiration of this Agreement, you must immediately cease use of the Product and destroy all copies of the Product.

2.9. No Rights Upon Termination. Upon termination of this Agreement you will no longer be authorized to Operate or use the Product in any way.

3. Support and Updates.

3.1. Terms of Support. During the one-year period or any other period specified in your Purchase Order you are entitled to technical services and support for the Product which is provided to you by Licensor during the regular business hours (GMT+ 03:00), except for locally-observed holidays, and includes the support provided through a special technical support section of the Licensor's site (the "Site"). During such support period e-mail support is unlimited and includes technical and support questions and patch fixes.

3.2. Updates. During the one-year period or any other period specified in your Purchase Order, you may download Updates to the Product when and as the Licensor publishes them on the Site, or through other online services. If the Product is an Update to a previous version of the Product, you must possess a valid license to such previous version in order to use the Update. You may continue to use the previous version of the Product on your Client Device after you receive the Update to assist you in the transition to the Update, provided that: (i) the Update and the previous version are installed on the same Client Device; (ii)

the previous version or copies thereof are not transferred to another party or Client Device unless all copies of the Update are also transferred to such party or Client Device; (iii) you acknowledge that any modification that you made to the Product may be lost, altered, distorted or destroyed rendering such modifications, Product or the part thereof inoperable or non-usable; and (iv) you acknowledge that any obligation the Licensor may have to support the previous version of the Product may be ended upon availability of the Update. Except for the rights to free Updates during the specified period, as further defined herein, nothing in this Agreement shall be construed as to grant you any rights or licenses with regard to the new releases of the Product or to entitle you to any new release. This Agreement does not obligate the Company to provide any Updates. Notwithstanding the foregoing, any Updates that you may receive become part of the Product and the terms of this Agreement apply to them (unless this Agreement is superseded by a succeeding agreement accompanying such Update or modified version of the Product).

4. Restrictions.

4.1. No Transfer of Rights. You may not transfer any rights pursuant to this Agreement nor rent, sublicense, lease, loan or resell the Product. You may not permit third parties to benefit from the use or functionality of the Product via a timesharing, service bureau or other arrangement, except to the extent such use is specified in the application price list, Purchase Order or product packaging for the Product. Except as otherwise provided in Section 1.2 hereof, you may not, without the Licensor's prior written consent, reverse engineer, decompile, disassemble or otherwise reduce any part of the Product to human readable form nor permit any third party to do so, except to the extent the foregoing restriction is expressly prohibited by applicable law. Notwithstanding the foregoing sentence, decompiling the Software is permitted to the extent the laws of your jurisdiction give you the right to do so to obtain information necessary to render the Software interoperable with other software; provided, however, that you must first request such information from the Licensor and the Licensor may, in its discretion, either provide such information to you (subject to confidentiality terms) or impose reasonable conditions, including a reasonable fee, on such use of the Software to ensure that the Licensor's and its affiliates' proprietary rights in the Software are protected. Except for the modification permitted under Section 1.2, you may not modify, or create derivative works based upon the Product in whole or in part.

4.2. Proprietary Notices and Copies. You may not remove any proprietary notices or labels on the Product. You may not copy the Product except as expressly permitted in Section 2 above.

4.3. Compliance with Law. You agree that in Operating the Product and in using any report or information derived as a result of Operating this Product, you will comply with all applicable international, national, state, regional and local laws and regulations, including, without limitation, privacy, trademark, patent, copyright, export control and obscenity law and you shall not use the Product for unethical or illegal business practices or in violation of any obligation to a third party in using, operating, accessing or running any of the Product and shall not knowingly assist any other person or entity to so violate any obligation to a third party.

All our Products licensed to You are absolutely legal and you can use them provided that you are the legal owner of all files or data you are going to recover through the use of our Products, you are the legal owner of any devices or cloud accounts access to which you are going to receive through the use of our Products, or have permission from the legitimate owner to perform these acts or have the legal authority to access such data on the basis of your national laws (i.e. you represent law enforcement agencies that can lawfully access such data in the course of investigation or otherwise or any other competent public authorities).

Any illegal use of our Products will be solely your responsibility.

Accordingly, you affirm that you have the legal right to access all data, information and files that have been hidden.

You further attest that the recovered or obtained otherwise data, passwords and/or files will not be used for any illegal purpose.

Be aware password recovery and the subsequent data decryption of unauthorized or otherwise illegally obtained files or unauthorized access to data and information may constitute theft or another wrongful action and may result in your civil and (or) criminal prosecution.

4.4. Additional Protection Measures. Solely for the purpose of preventing unlicensed use of the Product, the Software may install on your Client Device technological measures that are designed to prevent unlicensed use, and the Licensors may use this technology to confirm that you have a licensed copy of the Product. The update of these technological measures may occur through the installation of the Updates. The Updates will not install on unlicensed copies of the Product. If you are not using a licensed copy of the Product, you are not allowed to install the Updates.

The Licensors will not collect any personally identifiable information from your Client Device during this process.

5. WARRANTIES AND DISCLAIMERS.

5.1. Limited Warranty. The Licensors warrants that for 90 days (the "Warranty Period") from the date the Registration Code is provided to you by Licensors, the media on which Product has been provided will be free from defects in materials and workmanship and that the Software will perform substantially in accordance with the Documentation or generally conform to the Product's specifications published by the Licensors. Non-substantial variations of performance from the Documentation do not establish a warranty right. THIS LIMITED WARRANTY DOES NOT APPLY TO UPDATES AS APPLIED TO ANY MODIFIED PRODUCT, WHETHER OR NOT SUCH MODIFICATION IS PERMISSIBLE HEREUNDER, TRIAL AND EVALUATION VERSIONS, UPDATES, PRE-RELEASE, TRYOUT, PRODUCT SAMPLER, OR NOT FOR RESALE (NFR) COPIES OF PRODUCT. This limited warranty is void and your support right terminate if the defect has resulted from accident, abuse, or misapplication or any modification, whether or not such modification is permitted hereunder. No warranty is made as to the integrity, protection or safekeeping of any modification to the Products made by you upon installation of any of the Updates. To make a warranty claim, you must return the Product to the location where you obtained it along with proof of purchase within such sixty (60) day period of the license fee you paid for the Product. THE LIMITED WARRANTY SET FORTH IN THIS SECTION GIVES YOU SPECIFIC LEGAL RIGHTS. YOU MAY HAVE ADDITIONAL RIGHTS WHICH VARY FROM JURISDICTION TO JURISDICTION.

5.2. Customer Remedies. The Licensors and its suppliers' entire liability and your exclusive remedy for any breach of the foregoing warranty shall be at the Licensors' option: (i) return of the purchase price paid for the license, if any, (ii) replacement of the defective media in which the Product is contained, or (iii) correction of the defects, "bugs" or errors within reasonable period of time. You must return the defective media to the Licensors at your expense with a copy of your receipt. Any replacement media will be warranted for the remainder of the original warranty period.

5.3. NO OTHER WARRANTIES. EXCEPT FOR THE FOREGOING LIMITED WARRANTY, AND FOR ANY WARRANTY, CONDITION, REPRESENTATION OR TERM TO THE EXTENT TO WHICH THE SAME CANNOT OR MAY NOT BE EXCLUDED OR LIMITED BY LAW APPLICABLE TO YOU IN YOUR JURISDICTION, THE PRODUCT IS PROVIDED "AS-IS" WITHOUT ANY WARRANTY WHATSOEVER AND THE LICENSORS MAKES NO PROMISES, REPRESENTATIONS OR WARRANTIES, WHETHER EXPRESSED OR IMPLIED, WHETHER BY STATUTE, COMMON LAW, CUSTOM, USAGE OR OTHERWISE, REGARDING OR RELATING TO THE PRODUCT OR CONTENT THEREIN OR TO ANY OTHER MATERIAL FURNISHED OR PROVIDED TO YOU PURSUANT TO THIS AGREEMENT OR OTHERWISE. YOU ASSUME ALL RISKS AND RESPONSIBILITIES FOR SELECTION OF THE PRODUCT TO ACHIEVE YOUR INTENDED RESULTS, AND FOR THE INSTALLATION OF, USE OF, AND RESULTS OBTAINED FROM THE PRODUCT. THE LICENSORS MAKES NO WARRANTY THAT THE PRODUCT WILL BE ERROR FREE OR FREE FROM INTERRUPTION OR FAILURE, OR THAT IT IS COMPATIBLE WITH ANY PARTICULAR HARDWARE OR SOFTWARE. TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, LICENSORS DISCLAIMS ALL WARRANTIES, EITHER EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO IMPLIED WARRANTIES OF MERCHANTABILITY, NON-INFRINGEMENT OF THIRD PARTY RIGHTS, INTEGRATION, SATISFACTORY QUALITY OR FITNESS FOR ANY PARTICULAR PURPOSE WITH RESPECT TO

THE PRODUCT AND THE ACCOMPANYING WRITTEN MATERIALS OR THE USE THEREOF. SOME JURISDICTIONS DO NOT ALLOW LIMITATIONS ON IMPLIED WARRANTIES, SO THE ABOVE LIMITATION MAY NOT APPLY TO YOU. YOU HEREBY ACKNOWLEDGE THAT THE PRODUCT MAY NOT BE OR BECOME AVAILABLE DUE TO ANY NUMBER OF FACTORS INCLUDING WITHOUT LIMITATION PERIODIC SYSTEM MAINTENANCE, SCHEDULED OR UNSCHEDULED, ACTS OF GOD, TECHNICAL FAILURE OF THE SOFTWARE, TELECOMMUNICATIONS INFRASTRUCTURE, OR DELAY OR DISRUPTION ATTRIBUTABLE TO VIRUSES, DENIAL OF SERVICE ATTACKS, INCREASED OR FLUCTUATING DEMAND, AND ACTIONS AND OMISSIONS OF THIRD PARTIES. THEREFORE, THE LICENSOR EXPRESSLY DISCLAIMS ANY EXPRESS OR IMPLIED WARRANTY REGARDING SYSTEM AND/OR SOFTWARE AVAILABILITY, ACCESSIBILITY, OR PERFORMANCE. THE LICENSOR DISCLAIMS ANY AND ALL LIABILITY FOR THE LOSS OF DATA DURING ANY COMMUNICATIONS AND ANY LIABILITY ARISING FROM OR RELATED TO ANY FAILURE BY THE LICENSOR TO TRANSMIT ACCURATE OR COMPLETE INFORMATION TO YOU.

5.4. LIMITED LIABILITY; NO LIABILITY FOR CONSEQUENTIAL DAMAGES. YOU ASSUME THE ENTIRE COST OF ANY DAMAGE RESULTING FROM YOUR USE OF THE PRODUCT AND THE INFORMATION CONTAINED IN OR COMPILED BY THE PRODUCT, AND THE INTERACTION (OR FAILURE TO INTERACT PROPERLY) WITH ANY OTHER HARDWARE OR SOFTWARE WHETHER PROVIDED BY THE LICENSOR OR A THIRD PARTY. TO THE MAXIMUM EXTENT PERMITTED BY APPLICABLE LAW, IN NO EVENT WILL THE LICENSOR OR ITS SUPPLIERS OR LICENSORS BE LIABLE FOR ANY DAMAGES WHATSOEVER (INCLUDING, WITHOUT LIMITATION, DAMAGES FOR LOSS OF BUSINESS PROFITS, BUSINESS INTERRUPTION, LOSS OF BUSINESS INFORMATION, LOSS OF DATA, LOSS OF GOODWILL, WORK STOPPAGE, HARDWARE OR SOFTWARE DISRUPTION IMPAIRMENT OR FAILURE, REPAIR COSTS, TIME VALUE OR OTHER PECUNIARY LOSS) ARISING OUT OF THE USE OR INABILITY TO USE THE PRODUCT, OR THE INCOMPATIBILITY OF THE PRODUCT WITH ANY HARDWARE SOFTWARE OR USAGE, EVEN IF SUCH PARTIES HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. IN NO EVENT WILL LICENSOR'S TOTAL LIABILITY TO YOU FOR ALL DAMAGES IN ANY ONE OR MORE CAUSE OF ACTION, WHETHER IN CONTRACT, TORT OR OTHERWISE EXCEED THE AMOUNT PAID BY YOU FOR THE PRODUCT. THIS LIMITATION OF LIABILITY SHALL NOT APPLY TO LIABILITY FOR DEATH OR PERSONAL INJURY TO THE EXTENT THAT APPLICABLE LAW PROHIBITS SUCH LIMITATION. FURTHERMORE, BECAUSE SOME JURISDICTIONS DO NOT ALLOW THE EXCLUSION OR LIMITATION OF LIABILITY FOR CONSEQUENTIAL OR INCIDENTAL DAMAGES, THE ABOVE LIMITATION MAY NOT APPLY TO YOU.

6. Indemnification.

6.1. Indemnification for Violations. Your Operating of the Product, your accessing your account with Licensor and your entering into this Agreement constitutes your consent and agreement to defend, indemnify and hold harmless Licensor and its affiliated companies, employees, contractors, officers and directors from any claim or demand, including reasonable attorney's fees arising out of your use of the Product in violation of this Agreement.

SPECIAL PROVISION APPLICABLE TO U.S. PERSONS AND ENTITIES.

7. U.S. Government-Restricted Rights.

7.1. Notice to U.S. Government End Users. The Product and accompanying Documentation are deemed to be "Commercial Items," as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation," respectively, as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §§227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial Items and (b) with only those rights, including any use, modification, reproduction, release, performance, display or disclosure of the Product and accompanying Documentation, as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States.

7.2. Export Restrictions. You acknowledge and agree that the Product may be subject to restrictions and controls imposed by the Export Administration Act and the Export Administration Regulations of the United States (the "Acts"). You agree and certify that neither the Product nor any direct product thereof is being or will be used for any purpose prohibited by the Acts. You may not Operate, download, export, or re-export the Product (a) into, or to a national or resident of, any country to which the United States has embargoed goods, or (b) to anyone on the United States Treasury Department's list of Specially Designated Nationals or the U.S. Commerce Department's Table of Deny Orders. By downloading or using the Product, you are representing and warranting that you are not located in, under the control of, or a national or resident of any such country or on any such list. You acknowledge that it is your sole responsibility to comply with any and all government export and other applicable laws and that the Licensor has no further responsibility for such after the initial license to you. You warrant and represent that neither the U.S. Commerce Department, Bureau of Export Administration nor any other U.S. federal agency has suspended, revoked or denied your export privileges.

8. Your Information and the Licensor's Privacy Policy.

8.1. Privacy Policy. You acknowledge receipt of and agree to the Licensor's privacy statement which is made available to you in connection with installation and is set forth in full at <http://www.elcomsoft.com/privacy.html>. You hereby expressly consent to the Licensor's processing of your personal data (which may be collected by the Licensor or its distributors) according to the Licensor's current privacy policy as of the date of the effectiveness hereof which is incorporated into this Agreement by reference. By entering into this Agreement, you agree that the Licensor may collect and retain information about you, including your name and email address. The Licensor employs other companies and individuals to perform certain functions on its behalf. Examples include fulfilling orders, delivering packages, sending postal mail and e-mail, removing repetitive information from customer lists, analyzing data, providing marketing assistance, processing credit card payments, and providing customer service. They have access only to personal information needed to perform their functions, but may not use it for other purposes. The Licensor publishes a privacy policy on its web site and may amend such policy from time to time in its sole discretion. You should refer to the Licensor's privacy policy prior to agreeing to this Agreement for a more detailed explanation of how your information will be stored and used by the Licensor. If "you" are an organization, you will ensure that each member of your organization (including employees and contractors) about whom personal data may be provided to the Licensor has given his or her express consent to the Licensor's processing of such personal data. Personal data will be processed by the Licensor or its distributors in the country where it was collected.

8.2. Public Announcements. The Licensor may identify you to the public as a customer of the Licensor and describe in a customer case study the services and solutions delivered by the Licensor to you. The Licensor may also issue one or more press releases, containing an announcement of the execution and delivery of this Agreement and/or the implementation of the Product by you. Nothing contained in this Section shall be construed as an obligation by you to disclose any of your proprietary or confidential information to any third party. In addition, you may opt- out from this Section by writing an opt-out request to the Licensor at <https://support.elcomsoft.com>.

9. Miscellaneous.

9.1. Governing Law; Jurisdiction and Venue. This Agreement shall be governed by and construed and enforced in accordance with the laws of the Russian Federation without reference to conflicts of law rules and principles. To the extent permitted by law, the provisions of this Agreement shall supersede any provisions of the Uniform Commercial Code as adopted or made applicable to the Products in any competent jurisdiction. This Agreement shall not be governed by the United Nations Convention on Contracts for the International Sale of Goods, the application of which is expressly disclaimed and excluded. The courts within the Russian Federation shall have exclusive jurisdiction to adjudicate any dispute arising out of this Agreement. You agree that this Agreement is to be performed in the Russian Federation and that any action, dispute, controversy, or claim that may be instituted based on this Agreement, or arising

out of or related to this Agreement or any alleged breach thereof, shall be prosecuted exclusively in the federal or state courts in of the Russian Federation and you, to the extent permitted by applicable law, hereby waive the right to change venue to any other state, county, district or jurisdiction; provided, however, that the Licenser as claimant shall be entitled to initiate proceedings in any court of competent jurisdiction.

9.2. Period for Bringing Actions. No action, regardless of form, arising out of the transactions under this Agreement, may be brought by either party hereto more than one (1) year after the cause of action has occurred, or was discovered to have occurred, except that an action for infringement of intellectual property rights may be brought within the maximum applicable statutory period.

9.3. Entire Agreement; Severability; No Waiver. This Agreement is the entire agreement between you and Licenser and supersedes any other prior agreements, proposals, communications or advertising, oral or written, with respect to the Product or to subject matter of this Agreement. You acknowledge that you have read this Agreement, understand it and agree to be bound by its terms. If any provision of this Agreement is found by a court of competent jurisdiction to be invalid, void, or unenforceable for any reason, in whole or in part, such provision will be more narrowly construed so that it becomes legal and enforceable, and the entire Agreement will not fail on account thereof and the balance of the Agreement will continue in full force and effect to the maximum extent permitted by law or equity while preserving, to the fullest extent possible, its original intent. No waiver of any provision or condition herein shall be valid unless in writing and signed by you and an authorized representative of Licenser provided that no waiver of any breach of any provisions of this Agreement will constitute a waiver of any prior, concurrent or subsequent breach. Licenser's failure to insist upon or enforce strict performance of any provision of this Agreement or any right shall not be construed as a waiver of any such provision or right.

9.4. Contact Information. Should you have any questions concerning this Agreement contact us at <https://support.elcomsoft.com>.

© 2021 ElcomSoft Co.Ltd. All rights reserved. The Product, including the Software and any accompanying Documentation, are copyrighted and protected by copyright laws and international copyright treaties, as well as other intellectual property laws and treaties.

Contacting us

[Top](#) [Previous](#) [Next](#)

For technical support, please contact us through the following form:

<https://support.elcomsoft.com/>

For all other requests please use this form:

<https://www.elcomsoft.com/company.html>

Please contact us in **English**.

Important compatibility notes

[Top](#) [Previous](#) [Next](#)

- You can view or change account properties (Administrator account, Account is locked/disabled, Password expired, Password never expires) for local user accounts only, but not for AD accounts.
- Some computers may require third-party mass storage drivers for RAID, SCSI, SAS and similar storage devices. You can load additional drivers after ESR was booted from a USB drive, or use drivers supplied with the program.
- If you use read-only media to boot ESR (such as a CD/DVD), you cannot save the password hashes back to the bootable disk. Use a different storage media for saving files.

Elcomsoft System Recovery is compatible with modern and legacy computers. While modern computers are equipped with UEFI, you may still encounter a PC that still uses the legacy BIOS. Some manufacturers shipping newer PCs equipped with UEFI are still using the term "BIOS" to avoid confusion. However, the vast majority of computers sold over the past decade are equipped with UEFI firmware instead of a BIOS.

If your computer runs UEFI, there are no special requirements to boot media. If, however, you are analyzing a legacy PC equipped with a BIOS, you will need to create a bootable media that is no larger than 32GB. There are some other restrictions to keep in mind when analyzing legacy BIOS PCs.

When creating a bootable media, ESR offers the choice of three boot options: BIOS, UEFI x64, and UEFI x32. You must select the correct option for the target computer. A vast majority of modern computers use **UEFI x64**, which is the default option. For legacy PCs, select **BIOS**. The last option, **UEFI x32**, is used in a few special cases such as some thin-and-light devices and nettops built on certain generations of the Intel Atom platform which, while supporting 64-bit instructions, are limited to the 32-bit instruction set.

Requirements for booting legacy BIOS computers

There are special requirements when booting legacy BIOS computers from USB media, as defined by Microsoft for Windows PE.

- The size of the USB media cannot be smaller than 256 megabytes.
- The size of the USB media cannot be larger than 32 GB.
- The USB media must report a drive type of Removeable, not Fixed.
- The USB media must be the first in the list of boot devices in the computer BIOS.
- The computer BIOS must support the extended INT 13h (xINT13) BIOS interrupt for USB media.
- The computer BIOS must support booting from USB media.
- The computer's USB controller must support bulk-only transport (BOT).

Please note that these requirements do not apply to reasonably modern computers equipped with UEFI. To give an idea, manufacturers started using UEFI instead of a BIOS some time around 2007.

ESR has been designed for maximum compatibility and should be able to boot even from external hard disk (USB or FireWire) including ones that are larger than 32 GB, but some restrictions still apply.

Please note that after you reset the password, you may lose access to the user's: web page credentials, file share credentials, DPAPI encrypted stuff, EFS-encrypted files and certificates with private keys (signed/encrypted e-mail).


Creating bootable media

[Top](#) [Previous](#) [Next](#)

To create a bootable USB media, start the ESRBOOT utility and follow a few simple steps:

- Accept the ElcomSoft end user license agreement
- Enter your license key
- Select an option for creating a bootable USB drive
- Insert the USB device you're about to make bootable (warning: all data on this disk will be deleted!)
- Select the USB device from the Destination drive drop-down box. Select Show compatible devices only to filter out internal storage devices; you may wish to switch it off only if ESRBOOT does not show your removable disk.
- The program verifies that the device can be configured to boot ESR; creates a special partition; creates a logical drive; formats the drive; makes this drive bootable; then copies the files (Windows PE and ESR itself).

Please note: when creating a bootable media, ESR offers the choice of three boot options: BIOS, UEFI x64, and UEFI x32. You must select the correct option for the target computer. A vast majority of modern computers use **UEFI x64**, which is the default option. For legacy PCs, select **BIOS**. The last option, **UEFI x32**, is used in a few special cases such as some thin-and-light devices and nettops built on certain generations of the Intel Atom platform which, while supporting 64-bit instructions, are limited to the 32-bit instruction set.



Booting from a CD or USB device

[Top](#) [Previous](#) [Next](#)

To boot your computer from a CD or USB device, make changes in the target computer's BIOS or UEFI shell to have the CD-ROM drive or USB device appear as the first device in the list of boot devices:

PhoenixBIOS Setup Utility

MainAdvancedSecurityPowerBootExit


CD-ROM Drive
+Removable Devices
+Hard Drive
Network boot from AMD Am79C970A

Item Specific Help

Keys used to view or configure devices:
<Enter> expands or collapses devices with a + or -
<Ctrl+Enter> expands all
<Shift + 1> enables or disables a device.
<+> and <-> moves the device up or down.
<n> May move removable device between Hard Disk or Removable Disk
<d> Remove a device that is not installed.

F1 Help ↑↓ Select Item -/+ Change Values F9 Setup Defaults
Esc Exit ↔ Select Menu Enter Select ► Sub-Menu F10 Save and Exit

Then, insert the ESR boot media and reboot.




Press any key, and ESR will start booting (creating the RAM drive and loading Windows PE):



If you boot from a USB device, the steps are generally the same, except there will be no Press any key... message during the boot process.


When ESR is booted, you will be presented with the license agreement; accept it to continue:



Mass-stogare drivers

[Top](#) [Previous](#) [Next](#)

If your system uses a non-standard mass-storage adapter (such as some SerialATA, SCSI, RAID or SAS extension cards), you may need to specify the appropriate drivers:



The list of local drives will be displayed. If you cannot see the system partition, press Load driver and browse for a disk that contains the appropriate drivers. ESR will load the driver specified, and update the list of available partitions. The Driver load status window will let you know whether the driver has been loaded successfully.


Database source and working mode

[Top](#) [Previous](#) [Next](#)

Database source


You can select local and Active Directory accounts. Working with AD requires launching ESR on the server (domain controller) running a Windows Server 2000/2003/2008/2012/2016/2019.

- Work with local computer accounts (SAM)
- Work with Active Directory accounts (ntds.dit)
- Work with domain cached accounts
- Tools to search for disk encryption keys
- Additional utilities



Working mode

- Change account password and properties
- Dump password hashes for further audit/recovery
- Backup Registry or Active Directory to archive
- Restore Registry or AD from backup
- SAM database editor
- Reset DSRM password



If you already changed some account properties or password(s) and would like to roll back the changes, select the last option: Restore Registry or AD from backup. You will be prompted for locations of a backup copy of the Windows registry or AD database. Otherwise, select Change account password and properties (to change/reset passwords to user accounts, unlock disabled or locked accounts etc), or Dump password hashes... to dump password hashes from the AD or the registry into a text file for further analysis/recovery in [Proactive Password Auditor](#) or [Elcomsoft Distributed Password Recovery](#). Finally, you can back up the Registry (SAM, SECURITY and SYSTEM) or Active Directory database (ntds.dit).

When you dump local password hashes from the SAM, password history hashes are also extracted and saved into the dump file.


Password hashes can be saved as a standard dump file in ASCII or UNICODE. After dumping, the program prompts to open the file in Notepad; please note that if the user names or comments use non-US alphabet, they will be shown correctly only in UNICODE.

Finally, [SAM database editor](#) allows to edit all the fields in the SAM database that contain advanced properties of local user accounts.


Select operating system or SAM/AD files location

[Top](#) [Previous](#) [Next](#)


Once you selected a database source (SAM, DCC or AD) and working mode, you will be prompted to select the operating system to work with. If your system uses non-standard mass-storage adapters such as SCSI or SAS that are not supported by ESR, you may need to add drivers; see [Mass-storage drivers](#) for details. With the Auto selection, you can select the system folder from the drop-down box:



With Manual selection, you have to select the location of the AD database and SYSTEM Registry file using the [...] button at the right:



Alternatively, select the location of SAM, SECURITY and SYSTEM files:



In manual mode, we recommend to select the location of the SYSTEM file first, so the location of SAM/SECURITY (or AD database) will be filled automatically. The default location of SAM, SECURITY and SYSTEM files is:

%WINDOWS%\SYSTEM32\CONFIG\

The AD database (ntds.dit) is usually stored in the following folder:

%WINDOWS%\NTDS\

If you don't see the local drives when browsing for SAM/SECURITY/SYSTEM/AD files, it can mean that you do not have the necessary drivers installed such as SerialATA, SCSI or RAID. You may need to specify them during boot process (see [Booting from the CD or UFD](#) for details).

If your system uses a non-default SYSKEY mode (i.e. SYSKEY is not stored in the Registry), then the program will prompt you for the startup password or SYSKEY floppy disk. If you do not supply them, password hashes cannot be extracted, and you will be unable to change account passwords or properties, or even dump password hashes into a text file.

If you selected the Test short and simple passwords option, ESR will try to recover passwords using several pre-defined dictionary and brute-force attacks. It will also attempt to decrypt passwords that could be stored or cached in other files. While this attack may not recover a lot of passwords, it only takes minutes and helps to recover short and simple passwords. These passwords will be tested:


- Obvious combinations such as passwords that are equal to login names
- Stored dial-up passwords
- Passwords from secrets (SECURITY registry file)
- Passwords from some browsers that can be decrypted instantly
- LM passwords
 - 4-characters (caps, digits, 16 symbols)
 - Passwords from the wordlist
 - Passwords from the wordlist with one digit at the end
- NTLM passwords
 - 4 characters (small, digits, 16 symbols)
 - 4 characters (small, caps)
 - 5 characters (small)
 - 5 characters (caps)
 - 7 characters (digits)
 - 3 characters (all symbols)
 - Passwords from the wordlist
 - Repeatable combinations (like '00000', 'aaa' etc)
 - Keyboard combinations (like 'qwerty')
 - Keyboard combinations on OEM layout

After that, the program creates a few different mutations for passwords that have been found at previous steps, and tries to apply them to all accounts.

Local user accounts

[Top](#) [Previous](#) [Next](#)

If you work with local (SAM) accounts, you will be presented with a list of all local accounts after selecting the operating system or SAM and SYSTEM files:



The accounts that have Administrator privileges are highlighted in green. Accounts that are locked or disabled are colored red.

You can enable the Show password hashes option to see LM and NTLM hashes for all accounts with non-empty passwords, and Show password history option to see old records that are available (if saving the password history was enabled in the system).

Select the account you want to change the password or properties for, and press Next:

[ESR v7.06.671] Change account password (SAM)

SAM path: C:\Windows\system32\config\sam

SYSTEM path: C:\Windows\system32\config\system

Account name: Nick RID: 000003EB

Password: Password&094

Administrator flag
☒ Administrator account

Account type
☐ Temporary account
☒ Normal account
☐ MNS account
☐ Interdomain trust account
☐ Workstation trust account
☐ Server trust account

Password flags
☒ Password not required
☒ Password never expires
☐ Encrypted text password allowed
☐ Password expired

Misc flags
☐ Trusted for delegation
☐ Not delegated
☐ Trusted to auth for delegation
☐ Don't required preauth
☐ Use DES key only
☐ Account disabled
☐ Account is locked out
☐ Home directory required
☐ Smart card required

Password policy
 Minimum password length: 0 Password history length: 0

Password properties flag:

Items to change: user password, admin status

Help << Back Apply Close

Here you can reset/change the password as well as the following account properties:

- Administrator account
- Password never expires
- Password expired
- Account disabled
- Account is locked out

After you make the changes, press Apply. You will be prompted for the location and name of the backup copy of the SAM database.

Caution: do not reset the password with an empty one. For security reasons, select a new, reasonably complex password. Note that a local security policy might be applied. If this is the case, you will be able to set a non-compliant or even empty password, but you may be unable to log on with that new password if it does not comply the password policy. Finally, you cannot give Administrator privileges to built-in accounts such as Guest; it is also not recommended to change the password or any properties for any accounts in the Guests user group.

AD accounts


[Top](#) [Previous](#) [Next](#)

If you work with Active Directory accounts, you will get a list of all Active Directory accounts along with their properties. Here you can reset the password to any Active Directory user (including Domain Administrator), like for [local user accounts](#). However, you cannot change any of the account properties (like Administrator account, Password never expires etc).

Domain cached accounts


[Top](#) [Previous](#) [Next](#)

Once the Windows directory (or SECURITY and SYSTEM files) is selected, the program tries to locate and decrypt domain cached entries and display the list of cached user accounts.



Accounts with empty passwords are highlighted in blue. Accounts that are locked or disabled are colored red.

Select the account to change the password for, and press Next>> to proceed to the next step.



[ESR v7.06.671] Change account password (DCC)

SECURITY path: D:\win2\system32\config\security

SYSTEM path: D:\win2\system32\config\system

Account name: Alexei Alexandrov RID: 00000710

Password: |


Help << Back Apply Close

Type in a password or wipe out the appropriate input field, then press Apply. You will be prompted to back up the SECURITY file. It is highly recommended to backup the file before applying the changes.

To log on into the domain account after the password is reset, you will need to disable the connection to the domain. Otherwise, Windows will not use the cached credentials.

[Top](#) [Previous](#) [Next](#)

The SAM database editor allows viewing and changing most properties of local user accounts:



The following information is shown:

- General (user name, full name, comment, user ID)
- Hashes (LM and NTLM)
- Flags (essential user account properties)
- Account (time of last logon and logoff, password last set, account expiration, last bad password)
- Global and local groups (membership)
- Profile (home directory, script/profile path)
- Logon hours
- Misc (SAM database revision, country code, code page etc.)
- Domain information, properties and password properties


It is not recommended to edit any of the SAM database fields unless you know what you are doing.

Disk tools


[Top](#) [Previous](#) [Next](#)

In the disk tools dialog you can search for encrypted drives or virtual machines and dump encryption keys for further recovery using Elcomsoft Distributed Password Recovery or other tools.


You can also create a forensic disk image.



Once the program detects an encrypted drive, select it from the table and click Dump to save the disk encryption keys.



TrueCrypt/VeraCrypt disks require additional configuration. You may need to specify the encryption algorithms explicitly for faster recovery.



The program support for the following encryption types:

- BitLocker
- PGP Disk
- PGP WDE
- TrueCrypt
- VeraCrypt
- FileVault
- LUKS

Unlock BitLocker drives


[Top](#) [Previous](#) [Next](#)

To use a BitLocker-encrypted disk, you will need to unlock and mount it first. The program supports three general methods to unlock a BitLocker drive:

- Recovery Key. This method is used by default. Windows generates a 48-digit numeric recovery key every time a user initiates the BitLocker encryption.
- Password. A simple alphanumeric passphrase that is used to unlock BitLocker-encrypted disks in addition to the Recovery Key.
- USB Key. A binary file, typically with *.bek extension, that is stored on an external drive (eg. USB).

If the target computer is a part of a domain organization, you can also obtain the Recovery Key by contacting your domain administrator.

After the selected BitLocker disk is unlocked, the program decrypts and mounts the drive, allowing you to access the data stored on that disk.




The screenshot shows a window titled "[ESR v7.06.671] Unlock BitLocker drives". The window contains the following elements:

- Instructions:** "To unlock selected BitLocker drive, select one of the available unprotection methods. If the target PC is in a domain, you can obtain the recovery key by contacting your domain administrator."
- BitLocker-encrypted drive:** A dropdown menu showing "C:\".
- Show supported disk protectors only:** An unchecked checkbox.
- Disk protectors:** A blue bar showing "TPM And PIN, Recovery Key".
- Unprotect type:** A dropdown menu showing "Recovery Key".
- Numerical password:** A text box containing a 48-digit numeric recovery key placeholder: "XXXXXX-XXXXXX-XXXXXX-XXXXXX-XXXXXX-XXXXXX-XXXXXX-XXXXXX".
- Buttons:** "Help", "<< Back", "Unprotect" (highlighted with a blue border), and "Close".


Passwords and credentials

[Top](#) [Previous](#) [Next](#)


Main menu




Password hints



Wireless credentials



Windows keys

 **Windows product keys** [Minimize] [Maximize] [Close]

OS version:

OS owner:

Installed on:

Product name	Product id	Product key
Microsoft Windows	00329-10438-00000-AA252	
Microsoft Windows	03612-03291-043-800000-03-1033-1...	
Internet Explorer	00329-10438-00000-AA057	
Microsoft\Internet Explorer\Regi...	03612-03291-043-800000-03-1033-1...	
Microsoft\Windows NT\CurrentV...	03612-03291-043-800000-03-1033-1...	
Microsoft\Windows NT\CurrentV...		T3X2K-RCJVR-M4MVB-3D...
Microsoft\Windows NT\CurrentV...	00000-03289-000-000000-02-1033-1...	T3X2K-RCJVR-M4MVB-3D...
Microsoft\Windows NT\CurrentV...		VYBJV-BWP9G-X8VG7-4G9...
Microsoft\Windows NT\CurrentV...	55041-03291-043-800000-03-1033-1...	VYBJV-BWP9G-X8VG7-4G9...

[Help] [<< Back] [Next >>] [Close]

Miscellaneous

[Top](#) [Previous](#)

Some additional tools are available:

- CMD.EXE - the command line. You can use it to perform additional operations like copying files or launching built-in WinPE tools.
- FAR Manager - light and convenient file manager to explore the file system.
- SYSKEY - allows resetting or recovering the Syskey startup password.

